



By properly utilizing a top scrub and recoat routine, stripping frequency can be greatly reduced, a more uniform level of appearance can be maintained, and overall floor care costs can be dramatically lowered. A deep scrub removes soil in the top layer of the floor finish and prevents dirt from being trapped between recoats. This process removes 0.5 - 1 layer of finish.



People

- Team Assignments – 1 to 2 people. Who will be operating autoscrubber, applying scrubbing solution, mopping wall corners, using Doodle Bug, etc.?
- Safety Equipment – wet floor signs, please refer to product Safety Data Sheets.



Product & Equipment

- Dust mop
- Wet Floor signs
- Trident Auto-Scrubber
- Blue or green scrub pad; or 3M Surface Preparation Pads (SPP's)
- 3M Doodle Bug with Blue Scrub Pad
- 1 mop bucket with wringer
- 1 clean rayon mop with handle
- Hillyard Assurance® or Arsenal® Recoat Prep.





Procedures

1. Dust mop all flooring.
2. Set out Wet Floor signs.
3. Following label directions mix cleaner in auto-scrubber. Place Hillyard Defoam II in the recover tank.
4. Select the proper cleaning mode for deep scrubbing with Trident auto-scrubber.
 - a. Trident Plus Series Auto-scrubber – In Manual mode, select the “Scrubbing Only” mode.
Set Pad Pressure to HIGH, Water Distribution Level to MEDIUM, and Machine Speed to LOW.
 - b. Trident Pro Series Auto-scrubber –Set Pad Pressure to high using the Extra Brush Head Pressure button, Water Distribution Level to HIGH, and Machine Speed to LOW.
5. Scrub 500 – 1000 sq. ft sections of the floor, leaving behind the scrubbing solution. For best results, double scrub the floor. Perform the first scrubbing with the squeegee in the UP position leaving scrubbing solution behind on the floor.
6. After the first scrubbing use a doddle bug with a blue scrub pad to scrub corners and floor wall junctions not accessible with an auto-scrubber.
7. Lower the squeegee and perform the second scrub while recovering the scrubbing solution.
8. Once the entire floor is scrubbed, replace the scrubbing solution in the auto-scrubber with clean water, and switch out the scrub pad for a clean red or white cleaner pad.
9. Use the “Eco” cleaning setting on the Trident auto-scrubber to rinse the floor. Use a clean mop to rinse the wall junction and corners.
10. Clean equipment and store properly. Allow the floor to dry 30 minutes before applying finish.

