

Processing Procedure Super Daydream® Bath Blankets

PROCESSING REQUIREMENTS

Formula: This formula is only a guideline. Alterations should be made at the discretion of the laundry professional, based on specific requirements, supplies, equipment and experience.

<u>OPERATION</u>	<u>TIME</u>	<u>WATER LEVEL</u>	<u>TEMP.</u>	<u>SUPPLIES PER 100 LB. LOAD</u>
1. Break	10 min.	Low	160°F	8 oz. nonionic detergent & 16 oz. alkali
2. Suds	10 min.	Low	160°F	4 oz. nonionic detergent
3. Bleach	8 min.	Low	160°F	1 qt. 1% sodium hypochlorite
4. Rinse	3 min.	High	145°F	---
5. Rinse	3 min.	High	130°F	---
6. Rinse	3 min.	High	115°F	---
7. Sour/Softener	5 min.	Low	100°F	Sour to pH of 5.5 - 6.5

DRYING

After washing, tumble dry at an exhaust temperature of 160°F-180°F and use an appropriate cool down cycle.