

Windows Driver Installation Guide

Installation

Ensure to make a note of the location where the drivers were extracted as per the Quick-Start Guide instructions. This location will be used in a later step.

1. On the keyboard press the **Windows + R** keys. On the new **Pop-up Window** type **devmgmt.msc**. Press **Enter** to open the **Device Manager** screen.
2. Look for **Ethernet Control Device**. It will have a **!** or **? Sign** beside it.
3. **Right-click Ethernet Control Device** and click the **Update Driver** option.
4. On the screen, **How do you want to search for drivers** click **Browse my computer for drivers**.
5. On the screen, **Browse for drives on your computer** click **Let me pick from a list of available drivers on my computer**.
6. On the screen, **Select your device's type from the list below** click the **Show All Devices** option at the **Top** of the list to select it. Click the **Next** button.

Note: The *Select your device's type from the list below* screen does not appear on all systems. If you do not see this screen, skip this step.

7. On the screen, **Select the device driver you want to install for this hardware** click the **Have Disk** button.
 8. On the screen, **Install From Disk** click on the **Browse** button to open the **Windows File Explorer**. Navigate to the folder created when the **Drivers** were **Extracted**
- Open the folder corresponding to the **Windows Version**. Click on the **aqnic6xx.INF** file to select it. Click the **Open** button.

Note: To view your system type, 32-bit or 64-bit, press **Windows key + R** keys, type **control /name microsoft.system** and press **Enter**.

9. Click the **OK** button.
10. Click the **Next** button to finish the driver installation.

Verify Driver Installation

1. Navigate to the **Device Manager**.
2. Under **Network Adapters**, right-click **Marvell AQtion 10Gbit Network Adapter** and click the **Properties** option.
3. Confirm that the **Driver** is installed and working as expected.

